

**SDSAIRACONNPNT Version 1
Message Definition Record**

Sabre

**For
Sabre Data stream**

1/1/1995

Sabre Inc.

Date

06-05-2002

© 2000, Sabre Inc. All rights reserved.

This documentation is the confidential and proprietary intellectual property of Sabre Inc. Any unauthorized use, reproduction, preparation of derivative works, performance, or display of this document, or software represented by this document, without the express written permission of Sabre Inc. is strictly prohibited.

Sabre, the Sabre logo design, and (names of Sabre products) are trademarks and/or service marks of an affiliate of Sabre Inc. All other trademarks, service marks, and trade names are owned by their respective companies

Table of Contents

Table of Contents

Segment ID CON010

Segment ID CON060

CP01 SDSAIRACONNPNT Version 1
 Referance MDR : AIRAALCONPOINT
 CONNECT POINT DETAILS

Sample entry : T*CP-xxxxyy (x=brd point and y=offpoint) T*CP-LONLAX (GDS request entry)
 T*CP-MIAGCM

Segment ID CON010

Nesting Level 0 - Mandatory/Optional Flag O Repeat Factor 1

Element ID	Data Type	Min. Size	MAX. Size	Mandatory /Optional	Repeat Factor	Description	Example
01XS	N	1	4	S	1	MESSAGE NUMBER	
01XL	C	1	63	M	1	FREE TEXT	

Segment ID CON060

Nesting Level 0 - Mandatory/Optional Flag O Repeat Factor 1

Element ID	Data Type	Min. Size	MAX. Size	Mandatory /Optional	Repeat Factor	Description	Example
000K	C	1	5	S	1	Place of connection, coded	
00YT	C	1	1	O	1	INDICATOR (GENERIC)	
000K	C	1	5	S	1	Place of connection, coded	
00YT	C	1	1	O	1	INDICATOR (GENERIC)	
000K	C	1	5	S	1	Place of connection, coded	
00YT	C	1	1	O	1	INDICATOR (GENERIC)	
000K	C	1	5	S	1	Place of connection, coded	